
Virtual memory

- Came out of work in late 1960s by Peter Denning
 - Established working set model
 - Led directly to virtual memory

Want processes to co-exist



Consider multiprogramming on physical memory

- What happens if firefox needs to expand?
- If firefox needs more memory than is on the machine?
- If gcc has an error and writes to address 0x7100?
- When does gcc have to know it will run at 0x4000?
- What if vim isn't using its memory?

Issues in sharing physical memory

Protection

- A bug in one process can corrupt memory in another
- Must somehow prevent process A from trashing B's memory
- Also prevent A from even observing B's memory (ssh-agent)


Transparency

- A process shouldn't require particular physical memory bits
- Yet processes often require large amounts of contiguous memory (for stack, large data structures, etc.)
- Compilers often want fixed memory layout for performance

Resource exhaustion


- Programmers typically assume machine has "enough" memory
- Sum of sizes of all processes often greater than physical memory

Virtual memory goals



- Give each program its own virtual address space
 - At runtime, *Memory-Management Unit* relocates each load/store
 - Application doesn't see *physical* memory addresses
- Also enforce protection
 - Prevent one app from messing with another's memory
- And allow programs to see more memory than exists
 - Somehow relocate some memory accesses to disk


Virtual memory goals



- Give each program its own virtual address space
 - At runtime, *Memory-Management Unit* relocates each load/store
 - Application doesn't see *physical* memory addresses
- Also enforce protection
 - Prevent one app from messing with another's memory
- And allow programs to see more memory than exists
 - Somehow relocate some memory accesses to disk


Virtual memory advantages

- Can re-locate program while running
 - Run partially in memory, partially on disk
- Most of a process's memory may be idle (80/20 rule).




- Write idle parts to disk until needed
- Let other processes use memory of idle part
- Like CPU virtualization: when process not using CPU, switch (Not using a memory region? switch it to another process)
- Challenge: VM = extra layer, could be slow

Software Approach: load-time linking




- Linker patches addresses of symbols like printf
- Idea: link when process executed, not at compile time
 - Determine where process will reside in memory
 - Adjust all references within program (using addition)
- Problems?

Software Approach: load-time linking




- Linker patches addresses of symbols like printf
- Idea: link when process executed, not at compile time
 - Determine where process will reside in memory
 - Adjust all references within program (using addition)
- Problems?
 - How to enforce protection?
 - How to move once already in memory? (consider data pointers)
 - What if no contiguous free region fits program?

Dynamic Relocation: base + bound register




- Two special privileged registers: base and bound
- On each load/store/jump:
 - Physical address = virtual address + base
 - Check 0 ≤ virtual address < bound, else trap to kernel
- How to move process in memory?
- What happens on context switch?

Dynamic Relocation: base + bound register



- Two special privileged registers: base and bound
- On each load/store/jump:
 - Physical address = virtual address + base
 - Check 0 ≤ virtual address < bound, else trap to kernel
- How to move process in memory?
 - Change base register
- What happens on context switch?


Dynamic Relocation: base + bound register



- Two special privileged registers: base and bound
- On each load/store/jump:
 - Physical address = virtual address + base
 - Check 0 ≤ virtual address < bound, else trap to kernel
- How to move process in memory?
 - Change base register
- What happens on context switch?
 - OS must re-load base and bound register

Definitions


- Programs load/store to virtual addresses
- Actual memory uses physical addresses
- VM Hardware is Memory Management Unit (MMU)



- Usually part of CPU
- Configured through privileged instructions (e.g., load bound reg)
- Translates from virtual to physical addresses
- Gives per-process view of memory called address space

Definitions

- Programs load/store to virtual addresses
- Actual memory uses physical addresses
- VM Hardware is Memory Management Unit (MMU)



- Usually part of CPU
- Configured through privileged instructions (e.g., load bound reg)
- Translates from virtual to physical addresses
- Gives per-process view of memory called address space

Dynamic Relocation: trade-offs

Advantages

- Cheap in terms of hardware: only two registers
- Cheap in terms of cycles: do add and compare in parallel
- Examples: Cray-1 used this scheme

Disadvantages

Dynamic Relocation: trade-offs

Advantages

- Cheap in terms of hardware: only two registers
- Cheap in terms of cycles: do add and compare in parallel
- Examples: Cray-1 used this scheme

Disadvantages

- Growing a process is expensive or impossible
- No way to share code or data (E.g., two copies of vim)

• One solution: Multiple segments

- E.g., separate code, stack, data segments
- Possibly multiple data segments


free space

vim #1

gcc


vim #2

Segmentation



- Let processes have many base/bound regs
 - Address space built from many segments
 - Can share/protect memory at segment granularity
- Must specify segment as part of virtual address

Segmentation mechanics



- Each process has a segment table
- Each VA indicates a segment and offset:
 - Top bits of addr select segment, low bits select offset (PDP-10)
 - Or segment selected by instruction or operand (means you need wider "far" pointers to specify segment)

Segmentation example

- 2-bit segment number (1st digit), 12 bit offset (last 3)
 - Where is 0x0240? 0x1108? 0x265c? 0x3002? 0x1600?

Segmentation trade-offs

Advantages

- Multiple segments per process
- Allows sharing! (how?)
- Don't need entire process in memory

where?

Disadvantages


- Requires translation hardware, which could limit performance

gcc'

- Segments not completely transparent to program (e.g., default segment faster or uses shorter instruction)
- *n* byte segment needs *n contiguous* bytes of physical memory
- Makes fragmentation a real problem.

Fragmentation

- Fragmentation ⇒ Inability to use free memory
- Over time:
 - Variable-sized pieces = many small holes (external fragmentation)
 - Fixed-sized pieces = no external holes, but force internal waste (internal fragmentation)



Alternatives to hardware MMU

Language-level protection (Java)

- Single address space for different modules
- Language enforces isolation
- Singularity OS does this [Hunt]


Software fault isolation

- Instrument compiler output
- Checks before every store operation prevents modules from trashing each other
- Google Native Client does this

Paging


- Divide memory up into small pages
- Map virtual pages to physical pages
 - Each process has separate mapping
- Allow OS to gain control on certain operations
 - Read-only pages trap to OS on write
 - Invalid pages trap to OS on read or write
 - OS can change mapping and resume application
- Other features sometimes found:
 - Hardware can set "accessed" and "dirty" bits
 - Control page execute permission separately from read/write
 - Control caching or memory consistency of page

Paging trade-offs



- Eliminates external fragmentation
- Simplifies allocation, free, and backing storage (swap)
- Average internal fragmentation of .5 pages per "segment"


Simplified allocation



- Allocate any physical page to any process
- Can store idle virtual pages on disk

Paging data structures

- Pages are fixed size, e.g., 4K
 - Least significant 12 (log₂ 4K) bits of address are page offset
 - Most significant bits are page number
- Each process has a page table
 - Maps virtual page numbers (VPNs) to physical page numbers (PPNs)
 - Also includes bits for protection, validity, etc.




Example: Paging on PDP-11

- 64K virtual memory, 8K pages
 - Separate address space for instructions & data
 - I.e., can't read your own instructions with a load
- Entire page table stored in registers
 - 8 Instruction page translation registers
 - 8 Data page translations
- Swap 16 machine registers on each context switch

x86 Paging


- Paging enabled by bits in a control register (%cr0)
 - Only privileged OS code can manipulate control registers
- Normally 4KB pages
- %cr3: points to 4KB page directory
- Page directory: 1024 PDEs (page directory entries)
 - Each contains physical address of a page table
- Page table: 1024 PTEs (page table entries)
 - Each contains physical address of virtual 4K page
 - Page table covers 4 MB of Virtual mem
- See intel manual for detailed explanation
 - Also volume 2 of AMD64 Architecture docs
 - Also volume 3A of latest Pentium Manual

x86 page translation




*32 bits aligned onto a 4-KByte boundary

x86 page directory entry



x86 page table entry

Page-Table Entry (4-KByte Page)



x86 hardware segmentation

- x86 architecture also supports segmentation
 - Segment register base + pointer val = linear address
 - Page translation happens on linear addresses
- Two levels of protection and translation check
 - Segmentation model has four privilege levels (CPL 0-3)
 - Paging only two, so 0–2 = kernel, 3 = user
- Why do you want both paging and segmentation?

x86 hardware segmentation

- x86 architecture also supports segmentation
 - Segment register base + pointer val = linear address
 - Page translation happens on linear addresses
- Two levels of protection and translation check
 - Segmentation model has four privilege levels (CPL 0-3)
 - Paging only two, so 0–2 = kernel, 3 = user
- Why do you want both paging and segmentation?
- Short answer: You don't just adds overhead
 - Most OSes use "flat mode" set base = 0, bounds = 0xffffffff
 in all segment registers, then forget about it
 - x86-64 architecture removes much segmentation support
- Long answer: Has some fringe/incidental uses
 - VMware runs guest OS in CPL 1 to trap stack faults
 - OpenBSD used CS limit for W∧X when no PTE NX bit

Making paging fast

x86 PTs require 3 memory references per load/store

- Look up page table address in page directory
- Look up physical page number (PPN) in page table
- Actually access physical page corresponding to virtual address

For speed, CPU caches recently used translations

- Called a translation lookaside buffer or TLB
- Typical: 64-2K entries, 4-way to fully associative, 95% hit rate
- Each TLB entry maps a VPN → PPN + protection information

On each memory reference

- Check TLB, if entry present get physical address fast
- If not, walk page tables, insert in TLB for next time (Must evict some entry)

TLB details

- TLB operates at CPU pipeline speed ⇒ small, fast
- Complication: what to do when switch address space?
 - Flush TLB on context switch (e.g., old x86)
 - Tag each entry with associated process's ID (e.g., MIPS)
- In general, OS must manually keep TLB valid
- E.g., x86 invlpg instruction
 - Invalidates a page translation in TLB
 - Note: very expensive instruction (100–200 cycles)
 - Must execute after changing a possibly used page table entry
 - Otherwise, hardware will miss page table change
- More Complex on a multiprocessor (TLB shootdown)
 - Requires sending an interprocessor interrupt (IPI)
 - Remote processor must execute invlpg instruction

x86 Paging Extensions

PSE: Page size extensions

Setting bit 7 in PDE makes a 4MB translation (no PT)

PAE Page address extensions


- Newer 64-bit PTE format allows 36 bits of physical address
- Page tables, directories have only 512 entries
- Use 4-entry Page-Directory-Pointer Table to regain 2 lost bits
- PDE bit 7 allows 2MB translation

Long mode PAE

- In Long mode, pointers are 64-bits
- Extends PAE to map 48 bits of virtual address (next slide)
- Why are aren't all 64 bits of VA usable?

x86 long mode paging

Virtual Address



Where does the OS live?

• In its own address space?

- Can't do this on most hardware (e.g., syscall instruction won't switch address spaces)
- Also would make it harder to parse syscall arguments passed as pointers
- So in the same address space as process
 - Use protection bits to prohibit user code from writing kernel
- Typically all kernel text, most data at same VA in every address space
 - On x86, must manually set up page tables for this
 - Usually just map kernel in contiguous virtual memory when boot loader puts kernel into contiguous physical memory
 - Some hardware puts physical memory (kernel-only) somewhere in virtual address space

Hardware/Software Managed TLBs

Intel Evolution:

- 80286: Segmentation Only
- 80386: Segmentation + Paging
- AMD64/x86-64: Paging (segmentation basically removed)

Hardware Managed TLB: x86 hardware reloads the TLB

- Hardware reloads the TLB as needed from page tables
- Violations of protection bits lead to page faults

Software Managed TLB: MIPS, SPARC, Alpha, POWER

- Page fault triggered to ask OS to reload the TLB
- OS designs its own paging structure
- Hardware must provide fast exception handling

Very different MMU: MIPS

- Hardware checks TLB on application load/store
 - References to addresses not in TLB trap to kernel
- Each TLB entry has the following fields:
 Virtual page, Pid, Page frame, NC, D, V, Global
- Kernel itself unpaged
 - All of physical memory contiguously mapped in high VM (hardwired in CPU)
 - Kernel uses these pseudo-physical addresses
- User TLB fault hander very efficient
 - Two hardware registers reserved for it
 - utlb miss handler can itself fault—allow paged page tables
- OS is free to choose page table format!

MIPS Memory Layout

FFFF FFFF kseg2: Paged Kernel C000 0000 **Kernel Memory** BFFF FFFF kseg1: Phys. (Uncached) A000 0000 9FFF FFFF kseg0: Physical Memory 8000 0000 7FFF FFFF kuseg **User Memory User Paging** 0000 0000